

Android パーミッション

[Android]

・ <http://developer.android.com/reference/android/Manifest.permission.html>

Manifest.permission

パーミッション		内容	
ACCESS_CHECKIN_PROPERTIES	Allows read/write access to the "properties" table in the checkin database	to change values that get uploaded.	
ACCESS_COARSE_LOCATION	Allows an application to access coarse (e.g.	Cell-ID	WiFi) location
ACCESS_FINE_LOCATION	Allows an application to access fine (e.g.	GPS) location	
ACCESS_LOCATION_EXTRA_COMMANDS		Allows an application to access extra location provider commands	
ACCESS_MOCK_LOCATION		Allows an application to create mock location providers for testing	
ACCESS_NETWORK_STATE		Allows applications to access information about networks	
ACCESS_SURFACE_FLINGER		Allows an application to use SurfaceFlinger's low level features	
ACCESS_WIFI_STATE		Allows applications to access information about Wi-Fi networks	
ACCOUNT_MANAGER		Allows applications to call into AccountAuthenticators.	
AUTHENTICATE_ACCOUNTS		Allows an application to act as an AccountAuthenticator for the AccountManager	
BATTERY_STATS		Allows an application to collect battery statistics	
BIND_APPWIDGET		Allows an application to tell the AppWidget service which application can access AppWidget's data.	
BIND_DEVICE_ADMIN	Must be required by device administration receiver	to ensure that only the system can interact with it.	
BIND_INPUT_METHOD	Must be required by an InputMethodService	to ensure that only the system can bind to it.	
BIND_WALLPAPER	Must be required by a WallpaperService	to ensure that only the system can bind to it.	
BLUETOOTH		Allows applications to connect to paired bluetooth devices	

BLUETOOTH_ADMIN		Allows applications to discover and pair bluetooth <u>de</u> v <u>i</u> ces	
BRICK		Required to be able to disable the <u>de</u> v <u>i</u> ce (very dangerous!).	
BROADCAST_PACKAGE_REMOVED		Allows an application to broadcast a notification that an application package has been removed.	
BROADCAST_SMS		Allows an application to broadcast an SMS receipt notification	
BROADCAST_STICKY		Allows an application to broadcast sticky intents.	
BROADCAST_WAP_PUSH		Allows an application to broadcast a WAP PUSH receipt notification	
CALL_PHONE		Allows an application to initiate a phone call without going through the Dialer user interface for the user to confirm the call being placed.	
CALL_PRIVILEGED	Allows an application to call any phone number	including emergency numbers	without going through the Dialer user interface for the user to confirm the call being placed.
CAMERA		Required to be able to access the camera <u>de</u> v <u>i</u> ce.	
CHANGE_ <u>C</u> OMPONENT_ENABLED_STATE		Allows an application to change whether an application component (other than its own) is enabled or not.	
CHANGE_CONFIGURATION	Allows an application to modify the current configuration	such as locale.	
CHANGE_NETWORK_STATE		Allows applications to change network connecti <u>v</u> ity state	
CHANGE_WIFI_MULTICAST_STATE		Allows applications to enter Wi-Fi Multicast mode	
CHANGE_WIFI_STATE		Allows applications to change Wi-Fi connecti <u>v</u> ity state	
CLEAR_APP_CACHE		Allows an application to clear the caches of all installed applications on the <u>de</u> v <u>i</u> ce.	
CLEAR_APP_USER_DATA		Allows an application to clear user data	
CONTROL_LOCATION_UPDATES		Allows enabling/disabling location update notifications from the radio.	
DELETE_CACHE_FILES		Allows an application to delete cache files.	
DELETE_PACKAGES		Allows an application to delete packages.	
DEVICE_POWER		Allows low-level access to power management	

DIAGNOSTIC		Allows applications to RW to diagnostic resources.	
DISABLE_KEYGUARD		Allows applications to disable the keyguard	
DUMP		Allows an application to retrieve state dump information from system <u>services</u> .	
EXPAND_STATUS_BAR		Allows an application to expand or collapse the status bar.	
FACTORY <u>TEST</u>	Run as a manufacturer test application	running as the root user.	
FLASHLIGHT		Allows access to the flashlight	
FORCE_BACK		Allows an application to force a BACK operation on whatever is the top <u>activity</u> .	
GET_ACCOUNTS		Allows access to the list of accounts in the Accounts <u>Service</u>	
GET_PACKAGE_SIZE		Allows an application to find out the space used by any package.	
GET_TASKS	Allows an application to get information about the currently or recently running tasks: a thumbnail representation of the tasks	what <u>activities</u> are running in it	etc.
GLOBAL_SEARCH		This permission can be used on content <u>providers</u> to allow the global search system to access their data.	
HARDWARE <u>TEST</u>		Allows access to hardware peripherals.	
INJECT_EVENTS	Allows an application to inject user events (keys	touch	trackball) into the event stream and deliver them to ANY window.
INSTALL_LOCATION_PROVIDER		Allows an application to install a location <u>provider</u> into the Location Manager	
INSTALL_PACKAGES		Allows an application to install packages.	
INTERNAL_SYSTEM_WINDOW		Allows an application to open windows that are for use by parts of the system user interface.	
INTERNET		Allows applications to open network sockets.	
KILL_BACKGROUND_PROCESSES		Allows an application to call killBackgroundProcesses(String).	
MANAGE_ACCOUNTS		Allows an application to manage the list of accounts in the AccountManager	

MANAGE_APP_TOKENS	Allows an application to manage (create	destroy	Z-order) application tokens in the window manager.
MASTER_CLEAR			
MODIFY_AUDIO_SETTINGS		Allows an application to modify global audio settings	
MODIFY_PHONE_STATE	Allows modification of the telephony state - power on	mmi	etc.
MOUNT_FORMAT_FILESYSTEMS		Allows formatting file systems for removable storage.	
MOUNT_UNMOUNT_FILESYSTEMS		Allows mounting and unmounting file systems for removable storage.	
NFC		Allows applications to directly communicate over NFC	
PERSISTENT_ACTIVITY		This constant is deprecated. This functionality will be removed in the future; please do not use. Allow an application to make its activities persistent.	
PROCESS_OUTGOING_CALLS	Allows an application to monitor	modify	or abort outgoing calls.
READ_CALENDAR		Allows an application to read the user's calendar data.	
READ_CONTACTS		Allows an application to read the user's contacts data.	
READ_FRAME_BUFFER		Allows an application to take screen shots and more generally get access to the frame buffer data	
READ_HISTORY_BOOKMARKS		Allows an application to read (but not write) the user's browsing history and bookmarks.	
READ_INPUT_STATE		Allows an application to retrieve the current state of keys and switches.	
READ_LOGS		Allows an application to read the low-level system log files.	
READ_PHONE_STATE		Allows read only access to phone state.	
READ_SMS		Allows an application to read SMS messages.	
READ_SYNC_SETTINGS		Allows applications to read the sync settings	
READ_SYNC_STATS		Allows applications to read the sync stats	
REBOOT		Required to be able to reboot the device.	

RECEIVE_BOOT_COMPLETED	Allows an application to receive the ACTION_BOOT_COMPLETED that is broadcast after the system finishes booting.	
RECEIVE_MMS	Allows an application to monitor incoming MMS messages	to record or perform processing on them.
RECEIVE_SMS	Allows an application to monitor incoming SMS messages	to record or perform processing on them.
RECEIVE_WAP_PUSH	Allows an application to monitor incoming WAP push messages.	
RECORD_AUDIO	Allows an application to record audio	
REORDER_TASKS	Allows an application to change the Z-order of tasks	
RESTART_PACKAGES	This constant is deprecated. The restartPackage(String) API is no longer supported.	
SEND_SMS	Allows an application to send SMS messages.	
SET_ACTIVITY_WATCHER	Allows an application to watch and control how activities are started globally in the system.	
SET_ALARM	Allows an application to broadcast an Intent to set an alarm for the user.	
SET_ALWAYS_FINISH	Allows an application to control whether activities are immediately finished when put in the background.	
SET_ANIMATION_SCALE	Modify the global animation scaling factor.	
SET_DEBUG_APP	Configure an application for debugging.	
SET_ORIENTATION	Allows low-level access to setting the orientation (actually rotation) of the screen.	
SET_PREFERRED_APPLICATIONS	This constant is deprecated. No longer useful	see addPackageToPreferred(String) for details.
SET_PROCESS_LIMIT	Allows an application to set the maximum number of (not needed) application processes that can be running.	
SET_TIME	Allows applications to set the system time	
SET_TIME_ZONE	Allows applications to set the system time zone	
SET_WALLPAPER	Allows applications to set the wallpaper	
SET_WALLPAPER_HINTS	Allows applications to set the wallpaper hints	
SIGNAL_PERSISTENT_PROCESSES	Allow an application to request that a signal be sent to all persistent processes	

STATUS_BAR	Allows an application to open	close	or disable the status bar and its icons.	
SUBSCRIBED_FEEDS_READ		Allows an application to allow access the subscribed feeds ContentProvider.		
SUBSCRIBED_FEEDS_WRITE				
SYSTEM_ALERT_WINDOW	Allows an application to open windows using the type TYPE_SYSTEM_ALERT	shown on top of all other applications.		
UPDATE_DEVICE_STATS				Allows an application to update device statistics.
USE_CREDENTIALS				Allows an application to request authtokens from the AccountManager
USE_SIP				Allows an application to use SIP service
VIBRATE				Allows access to the vibrator
WAKE_LOCK				Allows using PowerManager WakeLocks to keep processor from sleeping or screen from dimming
WRITE_APN_SETTINGS				Allows applications to write the apn settings
WRITE_CALENDAR				Allows an application to write (but not read) the user's calendar data.
WRITE_CONTACTS				Allows an application to write (but not read) the user's contacts data.
WRITE_EXTERNAL_STORAGE				アプリケーションに外部ストレージへの書き込みを許可
WRITE_GSERVICES				Allows an application to modify the Google service map.
WRITE_HISTORY_BOOKMARKS				Allows an application to write (but not read) the user's browsing history and bookmarks.
WRITE_SECURE_SETTINGS				Allows an application to read or write the secure system settings.
WRITE_SETTINGS				Allows an application to read or write the system settings.
WRITE_SMS				Allows an application to write SMS messages.
WRITE_SYNC_SETTINGS				Allows applications to write the sync settings